

The C Preprocessor

For GCC version 16.0.0 (pre-release)

(GCC)

Richard M. Stallman, Zachary Weinberg

Copyright © 1987-2025 Free Software Foundation, Inc.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation. A copy of the license is included in the section entitled “GNU Free Documentation License”.

This manual contains no Invariant Sections. The Front-Cover Texts are (a) (see below), and the Back-Cover Texts are (b) (see below).

(a) The FSF’s Front-Cover Text is:

A GNU Manual

(b) The FSF’s Back-Cover Text is:

You have freedom to copy and modify this GNU Manual, like GNU software. Copies published by the Free Software Foundation raise funds for GNU development.

GNU Free Documentation License	72
ADDENDUM: How to use this License for your documents	79
Index of Directives	80
Option Index	80
Concept Index	82

__REGISTER_PREFIX__

This macro expands to a single token (not a string constant) which is the prefix applied to CPU register names in assembly language for this target. You can use it to write assembly that is usable in multiple environments. For example, in the **m68k-aout** environment it expands to nothing, but in the **m68k-coff** environment it expands to a single **'%'**.

__USER_LABEL_PREFIX__

This macro expands to a single token which is the prefix applied to user labels (symbols visible to C code) in assembly. For example, in the **m68k-aout** environment it expands to an **'_'**, but in the **m68k-coff** environment it expands to nothing.

This macro will have the correct definition even if **-f(no-)underscores** is in use, but it will not be correct if target-specific options that adjust this prefix are used (e.g. the OSF/rose **-mno-underscores** option).

```

__SIZE_TYPE__
__PTRDIFF_TYPE__
__WCHAR_TYPE__
__WINT_TYPE__
__INTMAX_TYPE__
__UINTMAX_TYPE__
__SIG_ATOMIC_TYPE__
__INT8_TYPE__
__INT16_TYPE__
__INT32_TYPE__
__INT64_TYPE__
__UINT8_TYPE__
__UINT16_TYPE__
__UINT32_TYPE__
__UINT64_TYPE__
__INT_LEAST8_TYPE__
__INT_LEAST16_TYPE__
__INT_LEAST32_TYPE__
__INT_LEAST64_TYPE__
__UINT_LEAST8_TYPE__
__UINT_LEAST16_TYPE__
__UINT_LEAST32_TYPE__
__UINT_LEAST64_TYPE__
__INT_FAST8_TYPE__
__INT_FAST16_TYPE__
__INT_FAST32_TYPE__
__INT_FAST64_TYPE__
__UINT_FAST8_TYPE__
__UINT_FAST16_TYPE__
__UINT_FAST32_TYPE__
__UINT_FAST64_TYPE__
__INTPTR_TYPE__
__UINTPTR_TYPE__

```

These macros are defined to the correct underlying types for the `size_t`, `ptrdiff_t`, `wchar_t`, `wint_t`, `intmax_t`, `uintmax_t`, `sig_atomic_t`, `int8_t`, `int16_t`, `int32_t`, `int64_t`, `uint8_t`, `uint16_t`, `uint32_t`, `uint64_t`, `int_least8_t`, `int_least16_t`, `int_least32_t`, `int_least64_t`, `uint_least8_t`, `uint_least16_t`, `uint_least32_t`, `uint_least64_t`, `int_fast8_t`, `int_fast16_t`, `int_fast32_t`, `int_fast64_t`, `uint_fast8_t`, `uint_fast16_t`, `uint_fast32_t`, `uint_fast64_t`, `intptr_t`, and `uintptr_t` typedefs, respectively. They exist to make the standard header files `stddef.h`, `stdint.h`, and `wchar.h` work correctly. You should not use these macros directly; instead, include the appropriate headers and use the typedefs. Some of these macros may not be defined on particular systems if GCC does not provide a `stdint.h` header on those systems.

__CHAR_BIT__

Defined to the number of bits used in the representation of the `char` data type. It exists to make the standard header given numerical limits work correctly. You should not use this macro directly; instead, include the appropriate headers.

ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

```
Copyright (C)  year  your name.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.3
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover
Texts. A copy of the license is included in the section entitled ``GNU
Free Documentation License''.
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the “with...Texts.” line with this:

```
with the Invariant Sections being list their titles, with
the Front-Cover Texts being list, and with the Back-Cover Texts
being list.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

